

SpinTron 99

Setup Instructions

NOTE: *If New Install (No Software loaded previously) Just Do Step 3*

1. Make backup of the following Configuration files:

- C:\Program Files\SpinTron 99\SpinTron.reg (In Windows Explorer you will need to change your folder settings to SHOW ALL HIDDEN FILES or you will not be able to see the file SinTron.reg.
- C:\Program Files\SpinTron 99\SpinTron Controls Settings.dat
- C:\Program Files\SpinTron 99\Configurations\Cycle Configurations.dat
- C:\Program Files\SpinTron 99\Configurations\ValveTrain Configurations.dat
- After you setup the new version of SpinTron 99 you will need to copy these files back to these directories or the directory you install the software to.

2. Remove or uninstall SpinTron 99 software from the computer.

- Click on Start button, then Settings, Then Control Panel
- Double click on Add/Remove Programs icon
- In the list of installed programs that show up on the Add/Remove Programs Properties dialog window, Pick SpinTron 99.
- Click the Add/Remove button. Answer Yes to removing any Shared files.
- Reboot the Computer. (YOU MUST DO THIS STEP OR THE NEW INSTALL WILL NOT WORK)

3. Setup the new software.

- Put the SpinTron 99 CD in your CD drive.
- The SpinTron Setup program should start. If it doesn't then follow these steps.
- Click on Start button, and then Run.
- Type in the letter of your CD drive, then :\Setup.exe. (Example: D:\Setup.exe)
- Click on the Ok button.
- Follow the instruction and if you like, let it install to the default directory.

4. Copy backup Configuration files back to their original directory.

5. Call SpinTron Tech-support if you have Questions.

CIM Systems Inc.
David L. Lanham
Office: 281.756.8900
E-Mail: DavidLanham@CIMRobotics.com

Make sure that your computer has Interrupt 5 not being used by any devices and that DMA Channel 1 is also clear. You can check these settings by going into Device Manager on your computer.

For additional information refer to the SpinTron 99 Manual that is saved on the SpinTron 99 Install CD in Microsoft Word Format.